



Apogee FX Rack v1.0

Release Notes

What is the Apogee FX Rack ?

- A new Plugin Rack from Apogee for AUv2, VST, and AAX formats
- 4 Plugins available ModEQ6, ModComp, EQP-1A, Opto-3A

Important note for Element Series and Ensemble Thunderbolt users

This release **does not** include Element Series and Ensemble Thunderbolt DualPath DSP functionality. DualPath functionality will be included in the November 2018 update.

Known issues in v1.0

- Logic FX Rack Default setting not always recalled correctly
- Some meters and visualizers are not optimized, to be improved in next release
- Pro Tools Plugin Compare button not functioning correctly
- Pro Tools minimum supported buffer is 256, to be improved in future release
- Subtle noise heard in Compressors if some parameters are rapidly automated, to be fixed

System Requirements

- Mac OS X 10.12.6 or higher, 10.14 Mojave fully supported
- 4 GB minimum RAM, 8 GB or higher recommended
- Pace iLok account, free from <https://www.ilok.com/#!registration> - physical iLok not required

Officially supported DAWs

Note: Currently the maximum supported Sample Rate is 96kHz

- Logic Pro 10
- Pro Tools 12, Ultimate (ProTools 11 and lower not currently supported)
- Ableton Live 10
- Cubase 9.5 VST 1 & 2 (VST 3 not implemented in this release)
- Please note that any AUv2, VST 1&2m, or AAX fully compliant DAW should work

Before installing software



1. Turn off speakers and disconnect headphones
2. Close all open Apps including your DAW



Apogee FX Rack Installation Instructions


IMPORTANT INSTALLATION STEPS FOR APOGEE FX RACK FREE TRIAL

1. Download and install the [iLok License Manager](#)
2. Download the [Apogee FX Rack installer](#)
3. In your DAW, open the Apogee FX Rack plugin (Logic Pro X show below)




4. Click on any of the four FX - ModEQ 6, ModComp, EQP-1A or Opto-3A.


5. In the Activation window, click “**Try**” for each plugin to start its 30-day trial period.
If you have an Activation Code, click “**Activate**” to activate all licenses simultaneously.



6. In the License Account Login window, enter your iLok account credentials; click “Create new account” if you don’t have an iLok account.



7. In the Select a Location window, select the activation location - the Apogee FX Rack supports Hard Disk and iLok 2-3 locations.



System Requirements

- Mac OS X 10.12.6 or higher, 10.14 Mojave fully supported
- 4 GB minimum RAM, 8 GB or higher recommended
- Have iLok account, free from <https://www.ilok.com/#!/registration> - Physical iLok not required
- iLok License Manager software needs to be installed on your Mac

Officially supported DAW's

- Logic Pro 10
- Pro Tools 12, Ultimate (ProTools 11 and lower not currently supported)
- Ableton Live 10
- Cubase 9.5 VST 1 & 2 (VST 3 not implemented in this release)
- Please note that any AUv2, VST 1&2m, or AAX fully compliant DAW should work